

Suprema WEBINAR 2020

4 - BioStar 2 Features : Door - SIP - Elevator - Monitoring

Speaker



| Cyril AUDIAU |

Technical Support Engineer I Suprema Europe and North Africa

How can I find Webinar Contents?

Email

✓ After this webinar, Suprema Team will provide the presentation and the recorded video file to the registered emails. It will take 5 days after reviewing the files with including QA list.

Website (Suprema Technical Support Site)

After this webinar, you can also find the information with including QA list to the below site. Search

Suprema Webinar on the site. Or, simply google it.

https://support.supremainc.com




suprema webinar

support.supremainc.com > support > solutions 🔻

Suprema Webinar : Technical Support


SNS Channel & YouTube

✓ Plus, we will post the information to YouTube, Facebook, and LinkedIn. (Simply search it on each site)







* How I inquiry during Webinar session?



Please mouse over on the bottom of your screen, the 3 buttons as following will come out.






1) [Q&A] Box for leaving your question


✓ During doing webinar, you can leave your questions to **QA box anytime**.

Suprema agents in panels will answer in real time.

* How I inquiry during Webinar session?



2) [Raise Hand] for Question Session



Please click on [Raise Hand] on the menu bar if you have any questions. The color will turn to Green.

Host will allow to unmute your microphone and you will be available to unmute your microphone at the time.


But you can also click [Raise Hand] during webinar anytime if you have questions.


How I inquiry during Webinar session?

Notification: Question Session

- ✓ Between the presentation progress, We will have QA session to make the interactive webinar.
- ✓ You can leave your questions through QA box.
- ✓ Or you can raise your hand from the menu bar, and you will be available to **unmute** your microphone once the host confirms your sign from Attendee's list.
- ✓ When you speak through a microphone, please introduce your name and question.

 We will answer one by one, so please kindly wait for your turn.








- 1. Webinar Goal
- 2. Advanced access control: Thermal camera
- 3. SIP Configuration on BioStation A2 and FaceStation 2
- 4. Add an elevator and floor
- 5. Monitoring logs
- 6. Questions and Answers

0 - Who we are (company)

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A



Global Powerhouse in Biometrics, Security and Identity Solutions

Suprema is a leading global provider of biometrics and security. By combining world renowned biometric algorithms with superior engineering, Suprema has introduced a number of technology initiatives and innovations to the security industry over the last couple of decades.

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A

The best in biometrics and security

Suprema provides comprehensive security solutions for security.

Whatever you're looking for, you'll find a Suprema's product to suit your needs. From robust outdoor Biometric Readers to discreet products for sensitive environments, we offer it all.








Biometrics Platform with Easy Use, Installation and Integration

BioStar2, Web-based open integrated security platform.





0 – Who we are (platform)

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A

Biometrics Platform with Easy Use, Installation and Integration

BioStar2, Web-based open integrated security platform.



E – Multi finger reader (Governmental)

- A User Management
- B Fingerprint Template
- C Face Template
- D Encryption for reader network

- F Web design
- G GDPR compliance
- H Encryption for web access
- I Encryption for Database



- 1. Webinar Goal
- 2. Advanced access control: Thermal camera
- 3. SIP Configuration on BioStation A2 and FaceStation 2
- 4. Add an elevator and floor
- 5. Monitoring logs
- 6. Questions and Answers

1 - Webinar Goal

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A

- How to add Thermal camera to Access Control reader
- How to enable SIP feature on BSA2 and FS2
- How to add elevator in BioStar2
- How to add floor in BioStar2
- Discovering Monitoring feature



- 1. Webinar Goal
- 2. Advanced access control: Thermal camera
- 3. SIP Configuration on BioStation A2 and FaceStation 2
- 4. Add an elevator and floor
- 5. Monitoring logs
- 6. Questions and Answers

2 – Advanced access control: Thermal camera

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A

To make this feature available we need:

- Thermal camera with IO relay
- Specific English resource file for BioStar 2 v2.7.14
- Specific Update resource file for FaceStation 2

Support on FreshDesk:

https://support.supremainc.com/en/support/solutions/articles/24000054419--biostar-2-thermal-camera-integration-with-suprema-access-control-system

Camera that are compatible and that have been tested:

Hikvision Dahua

DS-2TD1217B-3/PA (Dome Type) DH-TPC-BF5421-T

DS-2TD1217B-6/PA (Dome Type) DH-TPC-BF3221-T

DS-2TD1217B-0/TA (Bullet Type)

DS-2TD2617B-3/PA (Bullet Type)


DS-2TD2617B-6/PA (Bullet Type)





2 - Advanced access control: Thermal camera

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A



- 1. Webinar Goal
- 2. Advanced access control: Thermal camera
- 3. SIP Configuration on BioStation A2 and FaceStation 2
- 4. Add an elevator and floor
- 5. Monitoring logs
- 6. Questions and Answers


3 – SIP configuration

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A

What do you need to get interphone feature working on BioStation A2 or FaceStation 2:

- SIP server (http://www.raspberry-asterisk.org/) or SIP Line from provider
- FaceStation 2 or BioStation A2
- SIP Phone
- Knowledge base link below:

http://kb.supremainc.com/knowledge/doku.php?id=en:tc_appnote_setting_up_a_voip_server_for_a2&s[]=sip_http://kb.supremainc.com/knowledge/lib/exe/fetch.php?media=en:sip_server_configuration_guide_for_a2.pdf








<u>20</u>

3 – SIP configuration

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A

Latest release tested is: Asterisk 13.13.1 and FreePBX 13.0.190.11












3 – SIP configuration

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A



- 1. Webinar Goal
- 2. Advanced access control: Thermal camera
- 3. SIP Configuration on BioStation A2 and FaceStation 2
- 4. Add an Elevator and floor
- 5. Monitoring logs
- 6. Questions and Answers

4 - Add elevator and floor

1. Webinar Goal 2. What is BioStar 2 Software 3. How to install with MariaDB 4. How to install with MSSQL 5. Quick Tour on simple features 6. Q&A

Access Control License

Items		Starter (free of charge)	Basic	Standard	Advanced	Professional	Enterprise
Access Control	No. of Doors	5	20	50	100	300	1,000
	Maximum No. of Connected Devices	1,000	1,000	1,000	1,000	1,000	1,000
	Maximum No. of Access Levels 17	2,048	2,048	2,048	2,048	2,048	2,048
	Maximum No. of Access Groups ¹⁰	2,048	2,048	2,048	2,048	2,048	2,048
	Maximum No. of Access Groups per User	16	16	16	16	16	16
	Maximum No of Access Levels per Access Group	128	128	128	128	128	128
	Access Group Auto Sync	v	w	v	v	v	v
Users	Maximum No. of Cards per User	8	8	8	8	8	8
	Maximum No. of Fingerprints per User	10	10	10	10	10	10
	User Auto Sync	v	w	v	v	v	v
	Access-on-Card	v	w	¥	v	v	v
	Security Credential Cards	v	w	v	v	v	v
	ICLASS Secus Card	v	w	v	v	v	v
	Inactivation User Reports	v	w	v	v	v	v
	Custom Field	v	w	v	v	v	v
Elevator Control	Elevators	-	-	-	v	v	v
	Maximum No. of Floors per Elevator	-	-	-	192	192	192
	Maximum No. of Floor Levels	-	-	-	128	128	128
Zones	Anti-Pasaback	∆(Door)	∆(Door)	¥	v	v	v
	Fire Alarm	-	-	v	v	v	v
	Schedule Lock/Unlock	-	-	v	v	v	v
	Intrusion Alarm Zone	-	-	v	v	v	v
	Interlock Zone	-	-	v	v	v	v
	Muster Zone	-	-	¥	v	v	v
Advanced Features	Deshboard	v	w	¥	v	v	v
	Cloud	-	-	v	v	v	v
	Server Matching	-	-	-	v	v	v
	Audit Trail	v	w	v	v	v	v
	Daylight Saving Time	v	w	¥	v	v	٧
	Dual Authentication	v	w	¥	v	v	٧
Monitoring	Graphic Map	-	-	-	v	v	v

First, you will need a license for BioStar 2 for Access Control.

Then you will need also an OM-120 Device








4 - Add elevator and floor


1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A



- 1. Webinar Goal
- 2. Advanced access control: Thermal camera
- 3. SIP Configuration on BioStation A2 and FaceStation 2
- 4. Adding an elevator and floor
- 5. Monitoring logs
- 6. Questions and Answers

5- Monitoring logs

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A



- 1. Webinar Goal
- 2. Advanced access control: Thermal camera
- 3. SIP Configuration on BioStation A2 and FaceStation 2
- 4. Adding an elevator and floor
- 5. Monitoring logs
- 6. Questions and Answers

1. Webinar Goal 2. Thermal camera 3. SIP Configuration 4. Elevator - Floor 5. Monitoring 6. Q&A

Questions and Answers



Thank you!

